



Junior Detective

EDITION[®]

Introduction to Countries and Cultures

USER'S GUIDE WIN/MAC CD ROM

On this CD - check out demos for
other Carmen products! (Windows only)



Carmen Sandiego Junior Detective

EDITION®

Getting Started

The Carmen Sandiego Junior Detective Edition CD comes in three formats—Window 95, Windows 3.1, and Macintosh. This booklet covers all versions, so look below for the section that applies to you.

System Configuration: May require minor adjustments to the configuration of your operating system and/or updates to hardware component drivers.

Windows 95

System Requirements:

Windows 95

33MHz 386 or faster; 486 or faster recommended

8MB RAM

1MB hard disk space

CD-ROM drive required

Monitor/display card: SVGA 640x480, 256 colors

Windows compatible sound device

Before playing *Carmen Sandiego Junior Detective Edition*, you must first install a small portion of the program (approximately 700K) onto your hard disk. This operation makes it possible for you to establish a detective roster and keep track of your rank and merits.

To install the game, begin at the Windows 95 desktop. If you are not familiar with the Windows 95 desktop, please consult your Windows 95 manual. Insert the disc into your CD-ROM drive (using a disc caddy if appropriate).

The Brøderbund Startup-screen will automatically appear each time you insert the disc into your CD-ROM drive. (Your system may not be able to automatically display the Brøderbund Startup-screen. To bring up the Startup-screen manually, double-click on the CD-ROM drive icon in the *My Computer* group. Notice that when the *Carmen Sandiego Junior Detective Edition* disc is in the CD-ROM drive, the generic CD-ROM icon will be replaced by *Carmen Sandiego Junior Detective Edition* icon.)

Click on *Install* in the Brøderbund Startup-screen to begin the Setup program and follow the on-screen instructions to install the game.

We recommend you exit other Windows programs before installation. If you have already quit other Windows programs, then click *Next* to continue installing.

The Setup program will create a default directory, *C:\Program Files\Carmen Sandiego Junior*, and will then copy a number of files from the CD to this directory. If you wish, you may specify another directory by clicking *Browse*.

Please take a few moments to register *Carmen Sandiego Junior Detective Edition*. Registering your product qualifies you for free technical support and notification of future upgrades and special discounts.

To play *Carmen Sandiego Junior Detective Edition*:

Click *Start*, move the cursor to *Programs*, then to *Broderbund Software*. Click the *Carmen Sandiego Junior Detective Edition* menu item to begin the game. You may also play the game by clicking *Run* from the *Broderbund Startup*-screen that appears each time you insert the CD into the CD-ROM drive. If you deactivated the *Broderbund Startup*-screen, the game will automatically run when the CD is inserted in the CD-ROM drive.

To delete a player from the *Detective Roster*, press *Ctrl-D* when you reach the sign-in screen. Then click on the name you wish to delete.

Once you have launched the program and completed the sign-in sequence at the *ACME Detective Agency*, you can access a menu of game options by pressing *Ctrl-O* on your keyboard.

Note: You can skip through most animations, during the introduction and during the game, by pressing the **Space** bar.

Uninstall

After you have successfully installed *Carmen Sandiego Junior Detective Edition* to your hard drive, you may remove it from your hard drive. To uninstall the game, click *Start*, move the cursor to *Settings*, and then click *Control Panel*. Double-click the *Add/Remove Programs* icon. Select *Carmen Sandiego Jr. Edition* and click the *Add/Remove* button. Follow the on-screen instructions to uninstall the game. [Note: After uninstalling, the *Carmen Sandiego Junior Detective Edition* icon may still appear in the *Start* menu. Selecting this icon will not launch the game, since it has been uninstalled. The icon will disappear from the *Start* menu the next time you restart Windows 95.]

Deactivating and Reactivating the Startup-screen

This section applies only to users whose CD-ROM drive automatically reads the *Carmen Sandiego Junior Detective Edition* CD when it is inserted and displays the Brøderbund Startup-screen.

Each time you insert the *Carmen Sandiego Junior Detective Edition* disc into the CD-ROM drive, the Brøderbund Startup-screen will automatically appear. However, after you have installed the game this window can be deactivated so that it does not appear when the disc is inserted. When the window is deactivated, the game will automatically run when the CD is inserted.

To deactivate the Brøderbund Startup-screen:

Bring up the Brøderbund Startup-screen by inserting the CD into the CD-ROM drive. If the CD is already in the CD-ROM drive, double-click on the CD-ROM icon. The Brøderbund Startup-screen should display. At the bottom of the Brøderbund Startup-screen is the check-box marked, "Show window next time you insert CD." Click once on the check box, so that the check-mark disappears. Click the Close button or Run button to save the setting. The next time you insert the CD, or double-click on the CD-ROM drive icon, the Brøderbund Startup-screen will not appear, and the game will automatically run.

To reactivate the Brøderbund Startup-screen:

Insert the *Carmen Sandiego Junior Detective Edition* CD into your CD-ROM drive, and press Alt-F4 to immediately quit the game. Click once with the right mouse button on the CD-ROM drive icon in the My Computer group. (Note that when the *Carmen Sandiego Junior Detective Edition* disc is in the CD-ROM drive, the game icon and title will appear as the CD-ROM icon.) Select *AutoPlay Dialog* from the menu. The Brøderbund Startup-screen will appear.

At the bottom of the Brøderbund Startup-screen is the check-box marked, "Show window next time you insert CD." Click once on the box, so that the check mark appears. Click the *Close* button or *Run* button to save the setting. The next time you insert the CD, or double-click on the CD-ROM drive icon, the Brøderbund Startup-screen will appear.

Windows 3.1

System Requirements:

Windows 3.1

33MHz 386 or faster; 486 or faster recommended

4MB RAM (8MB recommended)

1MB hard disk space

CD-ROM drive

Monitor/display card: SVGA 640x480, 256 colors

Windows compatible sound device

Before playing *Carmen Sandiego Junior Detective Edition*, you must first install a small portion of the program (approximately 700K) onto your hard disk. This operation makes it possible for you to establish a detective roster and keep track of your rank and merits.

To install the game, begin at the Windows Program Manager. If you are not familiar with the Program Manager, consult your Windows manual. Insert the compact disc into your CD-ROM drive (using a disc caddy if appropriate).

Select *Run...* under the *File* menu. In the line labeled *Command Line*: type:

D:SETUP or E:SETUP

(depending on whether your CD-ROM drive is located at D or E) and click on the OK button.

The install program will create a default directory, C:\WORLDJR, and will then copy a number of files from the CD to this directory. If you wish, you may specify another directory during the installation process. The install program will create a program item called *Carmen Sandiego Junior Detective Edition* within a program group named *Broderbund Software*.

The installer will also run a MIDI sound setup program called *Carmen Sandiego Junior MIDI Setup*. Follow its directions to configure the program to make the best use of the MIDI capabilities of your sound card. In the future, you can run this setup program again by double-clicking on its icon in the *Broderbund Software* program group.

To play the game after you have completed the installation, double-click on the *Carmen Sandiego Junior Detective Edition* icon within the *Broderbund Software* program group. You may also run the game by choosing *Run...* from the *File* menu of either the Program Manager or File Manager. In the line labeled *Command Line:* type:

C:\WORLDJR\CARMEN

and click the OK button. If you installed the game to another directory or drive, modify the path accordingly.

To delete a player from the Detective Roster, press *Ctrl-D* when you reach the sign-in screen. Then click on the name you wish to delete.

Once you have launched the program and completed the sign-in sequence at the ACME Detective Agency, you can access a menu of game options by pressing *Ctrl-O* on your keyboard.

Note: You can skip through most animations, during the introduction and during the game, by pressing the **Space** bar.

Macintosh

System Requirements:

25MHz 68030 processor or faster; Power Macintosh

System 7.0.1 or higher

5MB RAM (8MB recommended); 3.6MB free

Requires 1MB hard disk space

CD-ROM drive (2X or faster recommended)

Video: 13 inch or larger monitor, 256 colors or shades of gray

Before playing *Carmen Sandiego Junior Detective Edition* for the first time, Sound Manager, Apple Multimedia Tuner, and Quicktime must be present in your *Extensions folder*. If you are using a Power Macintosh, you also need QuickTime Power Plug.

To check if you have any of these Extensions installed on your hard drive, double-click on the *System Folder*, then double-click on the *Extensions folder*. If an older version of the Extension you require is present, drag it to the Trash. (Note: you will not be able to empty the Extensions from your trash until you restart your computer.) Close the *Extensions folder* and the *System Folder*.

To install the required Extensions, double-click on the *Multimedia Extensions* folder icon on the *Carmen Sandiego Jr. Edition* CD. Position the window so that you can see its contents and the *System Folder* icon at the same time. Drag the appropriate Extension(s) from the *Multimedia Extensions* window onto the *System Folder* icon. This will copy the Extensions from the CD onto your hard drive.

When prompted with a dialog message to put the Extensions into the *Extensions* folder, click OK. When finished, restart your Macintosh.

Before running the game, make sure your monitor is set to display 256 colors. To do this, select *Control Panels* from your Apple () menu, double-click on the *Monitors* icon, and select 256 colors. If you do not see 256 colors as an option, you may need to install additional VRAM into your Macintosh.

To play the game, double-click on the *Carmen Sandiego Junior Edition* icon.

To delete a player from the Detective Roster, press *Option-D* when you reach the sign-in screen. Then click on the name you wish to delete.

Once you have launched the program and completed the sign-in sequence at the ACME Detective Agency, you can access a menu of game options by pressing *Option-O* on your keyboard.

If you would like to activate the menu bar at the top of the screen while playing the game, press *Option-M* on your keyboard.

Note: You can skip through most animations, during the introduction and during the game, by pressing the **Space** bar.

If You Can't Get Started

If you have followed the instructions in the previous section ("Getting Started") and you are still having problems loading or running the program, the following technical advice may help. Additional technical advice can be found in the Troubleshooting Guide included in the box with *Carmen Sandiego Junior Detective Edition*. If the advice in either of these documents does not solve your

problem, then see the end of this section, "When All Else Fails," to learn how to contact the Brøderbund Technical Support Department.

Window 3.1 and Windows 95

Video Display Problems

For the game to display properly, your Windows video driver must be set to display 256 colors. The game will not function with video drivers set to thousands or millions of colors. For instructions on changing Windows video display drivers, please refer to your Windows manual or the manual that came with your video board.

Screen Savers

Carmen Sandiego Junior Detective Edition usually will not have problems running on machines using After Dark or any other screen saver. However, should you encounter a problem, we recommend that you first disable your screen saver before running *Carmen Sandiego Junior Detective Edition*. To disable, please refer to the manual that came with your screen saver.

Windows 3.1

Not Enough Memory

Carmen Sandiego Junior Detective Edition requires that Windows has a total of 7,168K (7MB) of free memory. This amount may be a combination of physical and virtual memory. To check the amount of free memory currently available in

Windows, begin at the Windows Program Manager. Select *About Program Manager* from the *Help* menu. At the bottom of the information window will be a line titled *Memory* which will show the amount of free memory (in K) available in Windows.

If the total memory available to Windows is less than 7,168K try either shutting down other applications that may be running or increasing the size of your Windows Swap File (virtual memory). For additional information on these procedures, please refer to your Windows manual or the Troubleshooting Guide included in the box with this product.

No Sound

If you are unable to hear music or sound effects from the game, check to see if you have Windows sound drivers installed. To do this, begin at the Windows Program Manager. Double-click on the *Control Panel* icon located in the *Main* program group. Double-click on the *Sound* icon to open the Sound Control Panel.

If the items listed in the *Events* or *Files* dialog boxes are active (printed in black text), click on the *Test* button. If you do not hear event sounds, make sure your cables are fastened securely and that the volume controls for your sound device and speakers are set high enough to be audible. If the items listed in the *Events* or *Files* dialog boxes are grayed out, then Windows drivers for your sound device have not been properly installed. Please refer to the manual that came with your sound device for instructions on installing Windows sound drivers.

Adjusting Sound Levels

If you find there is an imbalance between the volume levels of the music and the characters' speech, we suggest you consult your sound system manual to make the appropriate adjustments between the wave and synthesized sounds. If this doesn't work, please contact your sound card manufacturer.

Wave or Midi Sound Device Not Responding

If you encounter this error message, you may need to update your sound drivers (wave and/or MIDI drivers) to the most recent versions provided by your sound device manufacturer.

Turning All Sound "Off" from the Options menu

A small number of sound cards do not allow us to control all aspects of sound playback from within the application. If you select All Sound "Off" and you still hear music with the photographer animations, villain animations, and/or capture animations, you may have one of these sound cards. If you wish to mute the program, you may always do so by turning down the volume directly on your speakers or sound card.

Macintosh

Memory

This program requires 3,600K (3.6MB) of available memory. To check your available memory, go to the Apple (🍏) menu and select *About This Macintosh*

or *About This Computer* (if you are using a Performa). *Total Memory* is the amount of physical RAM installed, *Largest Unused Block* is the amount of available memory.

On a Macintosh with 5MB (5,120K) total memory, you may need to free up additional memory by disabling Extensions. For information on how to turn off individual Extensions, please consult your Macintosh documentation or documentation accompanying the various Extensions you may have installed. (Be sure to keep the Apple Multimedia Tuner, Sound Manager and QuickTime Extensions active, as you will need them for the game to run!)

Sound Problems

If you are unable to hear music or sound effects from the game, check to see that the volume control in your *Sound Control Panel* is set high enough to be audible. To do this, select *Control Panels* from the Apple () menu, double click on the *Sound* icon, and set the volume to a higher level.

Video Display

This program requires your Macintosh to be set to display 256 colors. To do this, select *Control Panels* from the Apple menu, double-click on the *Monitors* control panel and select 256 colors. If you do not see 256 colors as an option, you may need to install additional VRAM (video memory) into your Macintosh.

Virtual Memory

This program requires Virtual Memory to be turned off. To turn this feature off,

select *Control Panels* from the Apple (🍏) menu, double-click on the *Memory* control panel, and set the Virtual Memory option to "Off." Close the *Memory* control panel and restart your computer for this change to take effect.

32-bit addressing

This program requires your Macintosh to operate in 32-bit addressing mode. To turn on 32-bit addressing, select *Control Panels* from the Apple (🍏) menu and double-click on the *Memory* control panel. You should see a 32-bit addressing option (this option does not appear if your computer only operates in 32-bit mode). Click the *On* button. Close the *Memory* control panel and restart your computer for this change to take effect.

Conflicts with System Extensions or Control Panel Devices

If this program appears to be running slowly, you might want to try turning off any unneeded Extensions that may be running. If you have any System Extensions which may interrupt game play or use needed memory (screen savers, for example) you may want to turn them off before you begin play. Please consult your Macintosh documentation or documentation accompanying the various Extensions you may have installed for information on how to turn off individual Extensions.

Player Roster

This program installs a file containing player information onto your hard drive. This file is called *CJrRoster*. It will first try to install the file into the *Preferences* folder inside your *System Folder*. If these folders are not labeled as such, the

program will create a folder called *Carmen Junior* and place the *CJrRoster* file inside it.

When All Else Fails

If you have followed these instructions and still have problems, please give Brøderbund Technical Support a call at (415) 382-4747 from 6 a.m. to 4:30 p.m. Monday through Thursday, 6 a.m. to 4 p.m. Friday Pacific Time. We will do our best to help you solve the problem. To help us solve your problem, have the computer near the phone and already started up. Be prepared to give us a detailed description of what happens when you try to run the program.

Acknowledgements

Lead Designer and Publisher

Ken Goldstein

Design Team

Leah Antignas
Michelle Bushneff
Louis Ewens
Ken Goldstein
Lance Groody
Leila Joslyn
Ralph Marsh

Produced by

Leah Antignas

Assistant Product Managers

Matt Fishboch
Courtney Greene
Sherman Dickman
Kira Shanti Meers
Keli Wong

Programmed by

Louis Ewens

Programming Assistants

Ken Bull
Carol Spellman
David Braun

Art Director

Michelle Bushneff

Lead Animator

Stuart Lowder

Graphics and Animation

Michelle Bushneff
Shirley Cochran
Kevin Dooley
Marcela Pesqueira Evans
Lydia Haggerty
Wendy Johnson
Stuart Lowder
Norman MacQueen
Jason Sadler
Michelle Sheller

Additional Graphics and Animations

William Browne
Michelle Graham
Robert King
Arnaldo Laboy
Barbara Lawrence
William Oliver
Nicole Tostevin
Prrfect Animation
Six-Foot-Two Productions

Original Music

Ralph Marsh
Jonelle Adkisson

Sound Design

Ralph Marsh
Haroon Tahir

Additional Sound Editing

Big Sound -
Roy Finch
Tom Hays

Screenplay by

Janis Diamond
Ken Goldstein
Sean Roche

Voice Talent

Leilani Jones - Dee Jaye
Rodger Bumpass -
The Chief
Scott Menville - Zack
Jennifer Hale - Ivy
and
Rita Moreno as
Carmen Sandiegra

Research

Miryam Acevedo-
Bouchard

Quality Assurance

Kirk Raulston and the
Brøderbund Quality
Assurance Department

Senior Marketing Manager

Bruce Friedrichs

Marketing Manager

Linda Dalton
Jennifer Apy

Assistant Marketing Manager

Karin Hohlbein

Marketing Coordinator

Maia Ellison
Valerie Schuldheisz

Manual and Package Design

Lynn Ross

Special Thanks to

Doug Carlston
Gary Carlston
Esteban Ahn
Glenn Axworthy
Marcus Badgley
John Baker
Judy Barnett
Larry Barbu
Brian Eheler
DIC Entertainment
Mike Foulger
Marsha Goodman
Daniel Goodwin
Terry Greenley
Leo Hourvitz
David Kessler
Laura Leininger
Robby London
Mickey Mantle
Tom Marcus
Nicole Martino
Bill McDonogh
Guy Nicholas
Andrew Pedersen
Tom Rettig
San Ramon School
Kermit Stewart
Laurie Strand
Ginny Walters
Harry Wilker

**Junior Agent
Handbook
Activity Design
and Art**

...the last word,
San Anselmo, CA
Linda Crawford
Liki La Porta
Lisa Pelo

Maps Courtesy of
Magellan
Geographix, Inc.,
Santa Barbara, CA

Location Photography
The location photo-
graphs in *Carmen*
San Diego Junior
Detective Edition were
provided by the follow-
ing image houses and
individual
photographers:

AllStock
VENEZUELA
George Hunter

**Robin Daugherty
Photography**
HONDURAS
Robin Daugherty

FPG International
ARGENTINA
M. Sutton
GERMANY

E. Nagele
INDIA
Telegraph Colour Lib.
UBYA
Richard Harrington
MALI
Dick Dietrich
NIGERIA
Robert Postner
PANAMA
Suzanne Murphy-Larro
PAPUA NEW GUINEA
Richard Rowan
PHILIPPINES
Jean Kugler
SOUTH AFRICA
FPG
SRI LANKA
Jean Kugler
VIETNAM
Jean Kugler
ZAIRE
Stan Osolinski

The Image Bank
AFGHANISTAN
John Lewis Stage
AUSTRALIA
Eric Meola Studio Inc.
CANADA
Douglas Stewart
Henderson
CHILE
Peter Miller
Actionpix, Inc.
CHINA
Harald Sund
EGYPT
David W. Hamilton
ENGLAND
Romilly Lockyer

ETHIOPIA
G & J Images, Inc.
GREECE
Antonio M. Rosario
INDONESIA
Steve Satushak
IRAN
Michael R. Schneps
JAPAN
Marc Solomon
KENYA
Alan Becker
MEXICO
Chuck Fishman
MOROCCO
Marc Romanelli
NEW ZEALAND
Toby Seger
PERU
Charles Weckler
RUSSIA
Tom Owen Edmunds
SAUDI ARABIA
Derek Berwin
SINGAPORE
Peter & Georgina Bowater
SOUTH KOREA
Kevin Forest
SPAIN
Cesar Lucas
THAILAND
Steve Niedorf
Photography
USA
Gerald Brimacombe

John Kreul Photography
CUBA
John Kreul
IRAQ
John Kreul

ThePhotoFile
ISRAEL
Jack Miller

Photovault
SOMALIA
Werner Krutein

**Norman Prince
Photography**
BOLIVIA
Norman Prince

Tony Stone Images
BRAZIL
Tony Stone Images
COLOMBIA
Erik Svenson
ECUADOR
Jeremy Horner
FRANCE
Malcolm Gilson
GUATEMALA
Michelle & Tom Grimm
ITALY
Robert Everts
JAMAICA
Elisa Leonelli
MADAGASCAR
Eriako Associates
SWEDEN
Steve Vidler
TURKEY
Peter Poulides
PAKISTAN
Craig Wells
POLAND
David Woodfall

Brøderbund 90 Day Satisfaction Guarantee

If you are not completely satisfied with your purchase, return the product to Brøderbund Software within 90 days of the date of purchase, along with the original sales receipt and the reason for return. Please state whether you would prefer another Brøderbund product of equal or lesser value, or a full refund. Limit 1 per household. Dealers, distributors and their employees are not eligible. Please call Brøderbund Software Direct at (415) 382-4745, or return the merchandise to Brøderbund Software, P.O. Box 6125, Novato, CA 94948-6125. If you wish to return the product via U.P.S., please send it to Brøderbund Software, Attention Customer Support, 775 SouthPoint Boulevard, Petaluma, CA 94954.

The Brøderbund 90 Day Satisfaction Guarantee also warrants for a period of 90 days that this copy of Carmen Sandiego Junior Detective Edition is free from substantial errors or defects that will materially interfere with the operation of the program as described in the enclosed user documentation. This policy applies to the initial purchaser only.

If you believe you have found any such error or defect in the program during the 90 day period, call Brøderbund's Technical Support Department at (415) 382-4747 from 6 a.m. to 4:30 p.m. Monday through Thursday, 6 a.m. to 4 p.m. Friday (Pacific Time). Brøderbund Technical personnel will attempt to help you correct or avoid the problem. If any such error or defect cannot be corrected or reasonably avoided, Brøderbund will inform you how to obtain a corrected program disk (or you inform Brøderbund that you prefer another Brøderbund product of equal or lesser value, or a full refund).

RESTRICTIONS

The Software contains copyrighted material, trade secrets and other proprietary material. In order to protect them, and except as permitted by applicable legislation, you may not decompile, reverse engineer, disassemble or otherwise reduce the Software to a human-perceivable form. You may not modify, network, rent, lease, loan, distribute or create derivative works based upon the Software in whole or in part. You may not electronically transmit the Software from one computer to another or over a network.

EXPORT LAW ASSURANCES

You agree and certify that neither the Software nor any other technical data received from Brøderbund, nor the direct product thereof, will be exported outside the United States except as authorized and as permitted by the laws and regulations of the United States. If the Software has been rightfully obtained by you outside of the United States, you agree that you will not re-export the Software nor any other technical data received from Brøderbund, nor the direct product thereof, except as permitted by the laws and regulations of the United States and the laws and regulations of the jurisdiction in which you obtained the Software.

GOVERNMENT END USERS

If you are acquiring the Software on behalf of any unit or agency of the United States Government, the following provisions apply. The Government agrees:

- (i) if the Software are supplied to the Department of Defense (DoD), the Software are classified as "Commercial Computer Software" and the Government is acquiring only "restricted rights" in the Software, and its documentation as that term is defined in Clause 252.227-7013(c)(1) of the DFARS; and
- (ii) if the Software are supplied to any unit or agency of the United States Government other than DoD, the Government's rights in the Software, and its documentation will be as defined in Clause 52.227-19(c)(2) of the FAR or, in the case of NASA, in Clause 18.52.227-86(d) of the NASA Supplement to the FAR.

DISCLAIMER OF WARRANTY

You expressly acknowledge and agree that use of the Software is at your sole risk. The Software, and related documentation are provided "AS IS" and without warranty of any kind. If for any reason you are dissatisfied with the software, return the product with your original sales receipt to Brøderbund within 90 days of the date of purchase for a full refund or a replacement product of equal or lesser value. Brøderbund and Brøderbund's licensor EXPRESSLY DISCLAIMS ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. BRØDERBUND DOES NOT WARRANT THAT THE FUNCTIONS CONTAINED IN THE SOFTWARE WILL MEET YOUR REQUIREMENTS, OR THAT THE OPERATION OF THE SOFTWARE WILL BE UNINTERRUPTED OR ERROR-FREE, OR THAT DEFECTS IN THE SOFTWARE AND THE FONTS WILL BE CORRECTED. FURTHERMORE, BRØDERBUND DOES NOT WARRANT OR MAKE REPRESENTATIONS REGARDING THE USE OR THE RESULTS OF THE USE OF THE SOFTWARE OR RELATED DOCUMENTATION IN TERMS OF THEIR CORRECTNESS, ACCURACY, RELIABILITY, OR OTHERWISE. NO ORAL OR WRITTEN INFORMATION OR ADVICE GIVEN BY BRØDERBUND OR A BRØDERBUND AUTHORIZED REPRESENTATIVE SHALL CREATE A WARRANTY OR IN ANY WAY INCREASE THE SCOPE OF THIS WARRANTY. SHOULD THE SOFTWARE PROVE DEFECTIVE, YOU (AND NOT BRØDERBUND OR A BRØDERBUND AUTHORIZED REPRESENTATIVE) ASSUME THE ENTIRE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION. SOME JURISDICTIONS DO NOT ALLOW THE EXCLUSION OF IMPLIED WARRANTIES, SO THE ABOVE EXCLUSION MAY NOT APPLY TO YOU.

LIMITATIONS ON WARRANTY

Unauthorized representations: Brøderbund warrants only that the program will perform as described in the user documentation. No other advertising, description or representation, whether made by a Brøderbund dealer, distributor, agent or employee, shall be binding upon Brøderbund or shall change the terms of this warranty.

NO CONSEQUENTIAL DAMAGES: BRØDERBUND SHALL NOT BE LIABLE FOR SPECIAL, INCIDENTAL, CONSEQUENTIAL OR OTHER DAMAGES, EVEN IF BRØDERBUND IS ADVISED OF OR AWARE OF THE POSSIBILITY OF SUCH DAMAGES. THIS MEANS THAT BRØDERBUND SHALL NOT BE RESPONSIBLE OR LIABLE FOR LOST PROFITS OR REVENUES, OR FOR DAMAGES OR COSTS INCURRED AS A RESULT OF LOSS OF TIME, DATA OR USE OF THE SOFTWARE, OR FROM ANY OTHER CAUSE EXCEPT THE ACTUAL COST OF THE PRODUCT. IN NO EVENT SHALL BRØDERBUND'S LIABILITY EXCEED THE PURCHASE PRICE OF THIS PRODUCT. SOME STATES DO NOT ALLOW THE EXCLUSION OR LIMITATION OF INCIDENTAL OR CONSEQUENTIAL DAMAGES, SO THE ABOVE LIMITATION OR EXCLUSION MAY NOT APPLY TO YOU.

You are entitled to use this product for your own use, but may not sell or transfer reproductions of the software or manual to other parties in any way, nor rent or lease the product to others without the prior written permission of Brøderbund. You may use one copy of the product on a single terminal connected to a single computer. You may not network the product or otherwise use it on more than one computer or computer terminal at the same time.


For technical support, on this or any other Brøderbund product, call 415/382-4700.

065





Carmen Sandiego™ Challenges Kids to Discover the World!




Ages 5 - 8

*Introduction to
Countries and Cultures*




Ages 9 & up

*USA Geography
and Regional Cultures*



Ages 9 & up

World Geography and Cultures



Visit www.carmensandiego.com



Broderbund®

All three products available for Windows® and Macintosh® CD-ROM

For more information about Broderbund and our products, write to us at P.O. Box 6125, Novato, CA 94948-6125. Visit our web site: www.broderbund.com
© Copyright 1996 Broderbund Software, Inc. All rights reserved. Where in the World is Carmen Sandiego?, Where in the USA is Carmen Sandiego?, Carmen Sandiego Junior Detective Edition, Carmen Sandiego, and Broderbund are trademarks and/or registered trademarks of Broderbund Software, Inc. 027 51406138